PREV CLASS NEXT CLASS

#### FRAMES NO FRAMES

SUMMARY: INNER | FIELD | CONSTR | METHOD DETAIL: FIELD | CONSTR | METHOD

# Class java.net.MulticastSocket

public class **MulticastSocket** extends <u>DatagramSocket</u>

The multicast datagram socket class is useful for sending and receiving IP multicast packets. A MulticastSocket is a (UDP) DatagramSocket, with additional capabilities for joining "groups" of other multicast hosts on the internet.

A multicast group is specified by a class D IP address, those in the range 224.0.0.1 to 239.255.255, inclusive, and by a standard UDP port number. One would join a multicast group by first creating a MulticastSocket with the desired port, then invoking the joinGroup(InetAddress groupAddr) method:

```
// join a Multicast group and send the group salutations
...
byte[] msg = {'H', 'e', 'l', 'l', 'o'};
InetAddress group = InetAddress.getByName("228.5.6.7");
MulticastSocket s = new MulticastSocket(6789);
s.joinGroup(group);
DatagramPacket hi = new DatagramPacket(msg, msg.length, group, 6789);
s.send(hi);
// get their responses!
byte[] buf = new byte[1000];
DatagramPacket recv = new DatagramPacket(buf, buf.length);
s.receive(recv);
...
// OK, I'm done talking - leave the group...
s.leaveGroup(group);
```

When one sends a message to a multicast group, **all** subscribing recipients to that host and port receive the message (within the time-to-live range of the packet, see below). The socket needn't be a member of the multicast group to send messages to it.

When a socket subscribes to a multicast group/port, it receives datagrams sent by other hosts to the group/port, as do all other members of the group and port. A socket relinquishes membership in a group by the leaveGroup(InetAddress addr) method. **Multiple MulticastSocket's** may subscribe to a multicast group and port concurrently, and they will all receive group datagrams.

Currently applets are not allowed to use multicast sockets.

#### Since:

JDK1.1

# **Constructor Summary**

## MulticastSocket()

Create a multicast socket.

## MulticastSocket(int port)

Create a multicast socket and bind it to a specific port.

Method Summary	
InetAddress	getInterface() Retrieve the address of the network interface used for multicast packets.
int	getTimeToLive() Get the default time-to-live for multicast packets sent out on the socket.
byte	getTTL()  Deprecated. use the getTimeToLive method instead, which allows you to get time-to-live values from 0 (excluded) to 255 (included).
void	joinGroup(InetAddress mcastaddr) Joins a multicast group.
void	leaveGroup(InetAddress mcastaddr) Leave a multicast group.
void	send(DatagramPacket p, byte ttl) Sends a datagram packet to the destination, with a TTL (time- to-live) other than the default for the socket.
void	setInterface(InetAddress inf) Set the outgoing network interface for multicast packets on this socket, to other than the system default.
void	setTimeToLive(int ttl) Set the default time-to-live for multicast packets sent out on this socket.
void	setTTL(byte ttl)  Deprecated. use the setTimeToLive method instead, which allows you to set time-to-live values from 0 (excluded) to 255 (included).

## Methods inherited from class java.net.DatagramSocket

 $\frac{close}{close}, \\ \underline{getLocalAddress}, \\ \underline{getLocalPort}, \\ \underline{getReceiveBufferSize}, \\ \underline{getSendBufferSize}, \\ \underline{getSendBuff$ 

## Methods inherited from class java.lang. Object

clone, equals, finalize, getClass, hashCode, notify, notifyAll, toString, wait, wait, wait

# **Constructor Detail**

## MulticastSocket

public MulticastSocket()

throws <u>IOException</u>

Create a multicast socket.

## MulticastSocket

Create a multicast socket and bind it to a specific port.

#### Parameters:

local - port to use

# **Method Detail**

### setTTL

**Deprecated.** use the setTimeToLive method instead, which allows you to set time-to-live values from 0 (excluded) to 255 (included).

Set the default time-to-live for multicast packets sent out on this socket. The TTL sets the IP time-to-live for DatagramPackets sent to a MulticastGroup, which specifies how many "hops" that the packet will be forwarded on the network before it expires.

This method may only be used to set time-to-live value between 1 and 127. The behavior if the value is outside that range is undefined.

#### **Parameters:**

ttl - the time-to-live

## setTimeToLive

Set the default time-to-live for multicast packets sent out on this socket. The TTL sets the IP time-to-live for DatagramPackets sent to a MulticastGroup, which specifies how many "hops" that the packet will be forwarded on the network before it expires.

The ttl is **must** be in the range 0 < ttl <= 255 or an IllegalArgumentException will be thrown.

### **Parameters:**

ttl - the time-to-live

## getTTL

**Deprecated.** use the getTimeToLive method instead, which allows you to get time-to-live values from 0 (excluded) to 255 (included).

Get the default time-to-live for multicast packets sent out on the socket. This method will truncate any time to live values greater than 127 to 127.

## getTimeToLive

Get the default time-to-live for multicast packets sent out on the socket.

## joinGroup

Joins a multicast group.

#### **Parameters:**

mcastaddr - is the multicast address to join

Throws:

<u>IOException</u> - is raised if there is an error joining or when address is not a multicast address.

## leaveGroup

Leave a multicast group.

#### **Parameters:**

mcastaddr - is the multicast address to leave

#### **Throws:**

<u>IOException</u> - is raised if there is an error leaving or when address is not a multicast address.

## setInterface

Set the outgoing network interface for multicast packets on this socket, to other than the system default. Useful for multihomed hosts.

## getInterface

Retrieve the address of the network interface used for multicast packets.

#### send

Sends a datagram packet to the destination, with a TTL (time- to-live) other than the default for the socket. This method need only be used in instances where a particular TTL is desired; otherwise it is preferable to set a TTL once on the socket, and use that default TTL for all packets. This method does **not** alter the default TTL for the socket.

#### **Parameters:**

p - is the packet to be sent. The packet should contain the destination multicast ip address and the data to be sent. One does not need to be the member of the group to send packets to a destination multicast address.

ttl - optional time to live for multicast packet. default ttl is 1.

#### Throws:

<u>IOException</u> - is raised if an error occurs i.e error while setting ttl.

#### See Also:

DatagramSocket.send(java.net.DatagramPacket),
DatagramSocket.receive(java.net.DatagramPacket)

### Overview Package Class Use Tree Deprecated Index Help

Java Platform 1.2

Beta 4

PREV CLASS NEXT CLASS

FRAMES NO FRAMES

SUMMARY: INNER | FIELD | CONSTR | METHOD

DETAIL: FIELD | CONSTR | METHOD

#### Submit a bug or feature

Submit comments/suggestions about new javadoc look

Java is a trademark or registered trademark of Sun Microsystems, Inc. in the US and other countries.

Copyright 1993-1998 Sun Microsystems, Inc. 901 San Antonio Road,

Palo Alto, California, 94303, U.S.A. All Rights Reserved.

This documentation was generated with a post-Beta4 version of Javadoc.